
tabula-py

Feb 22, 2023

Contents

| | |
|--|-----------|
| 1 Getting Started | 3 |
| 1.1 Requirements | 3 |
| 1.2 Installation | 3 |
| 1.3 Example | 4 |
| 2 FAQ | 5 |
| 2.1 tabula-py does not work | 5 |
| 2.2 I can't run from tabula import read_pdf | 5 |
| 2.3 I got a empty DataFrame. How can I resolve it? | 5 |
| 2.4 The result is different from tabula-java. Or, stream option seems not to work appropriately | 6 |
| 2.5 Can I use option xxxx? | 6 |
| 2.6 How can I ignore useless area? | 6 |
| 2.7 I faced ParserError: Error tokenizing data. C error. How can I extract multiple tables? | 8 |
| 2.8 I want to prevent tabula-py from stealing focus on every call on my mac | 8 |
| 2.9 I got ? character with result on Windows. How can I avoid it? | 8 |
| 2.10 I can't extract file/directory name with space on Windows | 8 |
| 2.11 I want to use a different tabula.jar file | 8 |
| 2.12 I want to extract multiple tables from a document | 9 |
| 2.13 Table cell contents sometimes overflow into the next row. | 9 |
| 2.14 I got a warning/error message from PDFBox including org.apache.pdfbox.pdmodel.. Is it the cause of empty dataframe? | 9 |
| 2.15 I can't figure out accurate extraction with tabula-py. Are there any similar Python libraries? | 9 |
| 3 Contributing to tabula-py | 11 |
| 3.1 Code formatting and testing | 11 |
| 3.2 Documentation | 11 |
| 4 tabula | 13 |
| 4.1 High level interfaces | 13 |
| 4.2 Internal interfaces | 27 |
| 5 tabula.errors | 29 |
| 6 Indices and tables | 31 |
| Python Module Index | 33 |

tabula-py is a simple Python wrapper of tabula-java, which can read table of PDF. You can read tables from PDF and convert into pandas's DataFrame. tabula-py also enables you to convert a PDF file into CSV/TSV/JSON file.

We highly recommend to look at [the example notebook](#) and try it on [Google Colab](#).

For high level API reference, see [*High level interfaces*](#).

CHAPTER 1

Getting Started

1.1 Requirements

- Java
 - Java 8+
- Python
 - 3.7+

1.2 Installation

Before installing tabula-py, ensure you have Java runtime on your environment.

You can install tabula-py from PyPI with pip command.

```
pip install tabula-py
```

Note: conda recipe on conda-forge is not maintained by us. We recommend to install via pip to use latest version of tabula-py.

1.2.1 Get tabula-py working (Windows 10)

This instruction is originally written by [@lahoffm](#). Thanks!

- If you don't have it already, install Java
- Try to run example code (replace the appropriate PDF file name).

- If there's a `FileNotFoundException` when it calls `read_pdf()`, and when you type `java` on command line it says '`java`' is not recognized as an internal or external command, operable program or batch file, you should set `PATH` environment variable to point to the Java directory.
- Find the main Java folder like `jre...` or `jdk....`. On Windows 10 it was under `C:\Program Files\Java`
- On Windows 10: **Control Panel -> System and Security -> System -> Advanced System Settings -> Environment Variables -> Select PATH -> Edit**
- Add the `bin` folder like `C:\Program Files\Java\jre1.8.0_144\bin`, hit `OK` a bunch of times.
- On command line, `java` should now print a list of options, and `tabula.read_pdf()` should run.

1.3 Example

`tabula-py` enables you to extract tables from a PDF into a DataFrame, or a JSON. It can also extract tables from a PDF and save the file as a CSV, a TSV, or a JSON.

```
import tabula

# Read pdf into a list of DataFrame
dfs = tabula.read_pdf("test.pdf", pages='all')

# Read remote pdf into a list of DataFrame
dfs2 = tabula.read_pdf("https://github.com/tabulapdf/tabula-java/raw/master/src/test/resources/technology/tabula/arabic.pdf")

# convert PDF into CSV
tabula.convert_into("test.pdf", "output.csv", output_format="csv", pages='all')

# convert all PDFs in a directory
tabula.convert_into_by_batch("input_directory", output_format='csv', pages='all')
```

See example notebook for more detail. I also recommend to read the tutorial article written by [@aegis4048](#).

Note: If you face some issue, we'd recommend to try `tabula.app` to see the limitation of `tabula-java`. Also, see [FAQ](#) as well.

CHAPTER 2

FAQ

2.1 tabula-py does not work

There are several possible reasons, but `tabula-py` is just a wrapper of `tabula-java`, make sure you've installed Java and you can use `java` command on your terminal. Many issue reporters forget to set PATH for `java` command.

You can check whether `tabula-py` can call `java` from Python process with `tabula.environment_info()` function.

2.2 I can't run from `tabula import read_pdf`

If you've installed `tabula`, it will be conflict the namespace. You should install `tabula-py` after removing `tabula`.

```
pip uninstall tabula
pip install tabula-py
```

2.3 I got a empty DataFrame. How can I resolve it?

`tabula-py` and `tabula-java` don't support image based PDF. It should contain text based table information.

Before tuning the `tabula-py` option, you have to check you set an appropriate `pages` option. By default, `tabula-py` extracts table from first page of your PDF, with `pages=1` argument. If you want to extract from all pages, you need to set `pages` option like `pages="all"` or `pages=[1, 2, 3]`. You might want to extract multiple tables from multiple pages, if so you need to set `multiple_tables=True` together.

Depending on the PDF's complexity, it might be difficult to extract table contents accuracy.

Tuning points of `tabula-py` are limited:

- Set specific area for accurate table detection

- Try `lattice=True` option for the table having explicit line. Or try `stream=True` option

To know the limitation of tabula-java, I highly recommend to use `tabula` app, the GUI version of `tabula-java`.

`tabula` app can:

- specify the area with GUI
- show preview of the extraction with lattice or stream mode
- export template that is reusable for `tabula-py`

Even if you can't extract `tabula-py` for those table contents which can be extracted `tabula` app appropriately, file an issue on GitHub.

2.4 The result is different from `tabula-java`. Or, `stream` option seems not to work appropriately

`tabula-py` set `guess` option `True` by default, for beginners. It is known to make a conflict between `stream` option. If you feel something strange with your result, please set `guess=False`.

2.5 Can I use option `xxx`?

Yes. You can use `options` argument as following. The format is same as `cli` of `tabula-java`.

```
read_pdf(file_path, options="--columns 10.1,20.2,30.3")
```

2.6 How can I ignore useless area?


In short, you can extract with `area` and `spreadsheet` option.

```
In [4]: tabula.read_pdf('./table.pdf', spreadsheet=True, area=(337.29, 226.49, 472.85, 384.91))
Picked up JAVA_TOOL_OPTIONS: -Dfile.encoding=UTF-8
Out[4]:
      Unnamed: 0  Col2  Col3  Col4  Col5
0        A      B    12      R      G
1      NaN      R      T    23      H
2        B      B    33      R      A
3        C      T    99      E      M
4        D      I    12    34      M
5        E      I      I      W    90
6      NaN      1      2      W      h
7      NaN      4      3      E      H
8        F      E    E4      R      4
```

2.6.1 How to use `area` option

According to `tabula-java` wiki, there is a explain how to specify the area: <https://github.com/tabulapdf/tabula-java/wiki/Using-the-command-line-tabula-extractor-tool#grab-coordinates-of-the-table-you-want>

For example, using macOS's preview, I got area information of this PDF:



| This is the header of the table | | | | |
|---------------------------------|------|------|------|------|
| Col1 | Col2 | Col3 | Col4 | Col5 |
| A | B | 12 | R | G |
| | R | T | 23 | H |
| B | B | 33 | R | A |
| C | T | 99 | E | M |
| D | I | 12 | 34 | M |
| E | I | I | W | 90 |
| | 1 | 2 | W | h |
| | 4 | 3 | E | H |
| F | E | E4 | R | 4 |
| G | 3 | D | R | 4 |

```
java -jar ./target/tabula-1.0.1-jar-with-dependencies.jar -p all -a $y1,$x1,$y2,$x2 -  
→o $csvfile $filename
```

given

```
# Note the left, top, height, and width parameters and calculate the following:
```

```
y1 = top  
x1 = left
```

(continues on next page)

(continued from previous page)

```
y2 = top + height  
x2 = left + width
```

I confirmed with tabula-java:

```
java -jar ./tabula/tabula-1.0.1-jar-with-dependencies.jar -a "337.29,226.49,472.85,  
→384.91" table.pdf
```

Without `-r`(same as `--spreadsheet`) option, it does not work properly.

2.7 I faced ParserError: Error tokenizing data. C error. How can I extract multiple tables?

This error occurs when pandas tries to extract multiple tables with different column size at once. Use `multiple_tables` option, then you can avoid this error.

2.8 I want to prevent tabula-py from stealing focus on every call on my mac

Set `java_options=["-Djava.awt.headless=true"]`. kudos @jakekara

2.9 I got ? character with result on Windows. How can I avoid it?

If the encoding of PDF is UTF-8, you should set `chcp 65001` on your terminal before launching a Python process.

```
chcp 65001
```

Then you can extract UTF-8 PDF with `java_options="-Dfile.encoding=UTF8"` option. This option will be added with `encoding='utf-8'` option, which is also set by default.

```
# This is an example for java_options is set explicitly  
df = read_pdf(file_path, java_options="-Dfile.encoding=UTF8")
```

Replace 65001 and UTF-8 appropriately, if the file encoding isn't UTF-8.

2.10 I can't extract file/directory name with space on Windows

You should escape file/directory name yourself.

2.11 I want to use a different tabula .jar file

You can specify the jar location via environment variable

```
export TABULA_JAR=".../tabula-x.y.z-jar-with-dependencies.jar"
```

2.12 I want to extract multiple tables from a document

You can use the following example code

```
df = read_pdf(file_path, multiple_tables=True)
```

The result will be a list of DataFrames. If you want separate tables across all pages in a document, use the pages argument.

2.13 Table cell contents sometimes overflow into the next row.

You can try using lattice=True, which will often work if there are lines separating cells in the table.

2.14 I got a warning/error message from PDFBox including org.apache.pdfbox.pdmodel.. Is it the cause of empty dataframe?

No.

Sometimes, you might see message like “ Jul 17, 2019 10:21:25 AM org.apache.pdfbox.pdmodel.font.PDType1Font WARNING: Using fallback font NimbusSanL-Regu for Univers. Nothing was parsed from this one.” This error message came from Apache PDFBox which is used under tabula-java, and this is caused by the PDF itself. Neither tabula-py nor tabula-java can’t handle the warning itself, except for silent option that suppress the warning.

2.15 I can't figure out accurate extraction with tabula-py. Are there any similar Python libraries?

I know tabula-py has limitation depending on tabula-java. Sometimes your PDF is too complex to tabula-py. If you want to find plan B, there are similar packages as the following:

- <https://github.com/jsvine/pdfplumber>
- <https://camelot-py.readthedocs.io/en/master/>

CHAPTER 3

Contributing to tabula-py

Interested in helping out? I'd love to have your help!

You can help by:

- [Reporting a bug.](#)
- Adding or editing documentation.
- Contributing code via a Pull Request.
- Write a blog post or spreading the word about tabula-py to people who might be able to benefit from using it.

3.1 Code formatting and testing

If you want to become a contributor, you can install dependency after cloning the repo as follows:

```
pip install -e .[dev, test]  
pip install nox
```

For running tests and linter, run nox command.

```
nox .
```

3.2 Documentation

You can build document on your environment as follows:

```
pip install -e .[doc]  
cd docs && make html
```

The documentation source is under `docs/` directory and the document is published on Read the Docs automatically.

CHAPTER 4

tabula

4.1 High level interfaces

4.1.1 tabula.io

This module is a wrapper of tabula, which enables table extraction from a PDF.

This module extracts tables from a PDF into a pandas DataFrame. Currently, the implementation of this module uses subprocess.

Instead of importing this module, you can import public interfaces such as `read_pdf()`, `read_pdf_with_template()`, `convert_into()`, `convert_into_by_batch()` from `tabula` module directory.

Note: If you want to use your own tabula-java JAR file, set `TABULA_JAR` to environment variable for JAR path.

Example

```
>>> import tabula  
>>> df = tabula.read_pdf("/path/to/sample.pdf", pages="all")
```

```
tabula.io.convert_into(input_path: Union[IO, str, os.PathLike], output_path: str, output_format: str  
                      = 'csv', java_options: Optional[List[str]] = None, pages: Union[str, int,  
                      List[int], None] = None, guess: bool = True, area: Union[Iterable[float],  
                      Iterable[Iterable[float]], None] = None, relative_area: bool = False, lat-  
                      tice: bool = False, stream: bool = False, password: Optional[str] = None,  
                      silent: Optional[bool] = None, columns: Optional[List[float]] = None, rel-  
                      ative_columns: bool = False, format: Optional[str] = None, batch: Op-  
                      tional[str] = None, options: str = "") → None
```

Convert tables from PDF into a file. Output file will be saved into `output_path`.

Parameters

- **input_path** (*file like obj*) – File like object of target PDF file.
- **output_path** (*str*) – File path of output file.
- **output_format** (*str, optional*) – Output format of this function (csv, json or tsv). Default: csv
- **java_options** (*list, optional*) – Set java options
"–Xmx256m".

Example

"–Xmx256m".

- **pages** (*str, int, list of int, optional*) – An optional values specifying pages to extract from. It allows *str*, ‘int’, *list* of *int*. Default: 1

Examples

'1-2,3', 'all', [1,2]

- **guess** (*bool, optional*) – Guess the portion of the page to analyze per page. Default *True* If you use “area” option, this option becomes *False*.

Note: As of tabula-java 1.0.3, guess option becomes independent from lattice and stream option, you can use guess and lattice/stream option at the same time.

- **area** (*list of float, list of list of float, optional*) – Portion of the page to analyze(*top, left, bottom, right*). Default is entire page.

Note: If you want to use multiple area options and extract in one table, it should be better to set *multiple_tables=False* for *read_pdf()*

Examples

[269.875,12.75,790.5,561], [[12.1,20.5,30.1,50.2], [1.0,3.2,10.5,40.2]]

- **relative_area** (*bool, optional*) – If all area values are between 0-100 (inclusive) and preceded by ‘%’, input will be taken as % of actual height or width of the page. Default *False*.
- **lattice** (*bool, optional*) – Force PDF to be extracted using lattice-mode extraction (if there are ruling lines separating each cell, as in a PDF of an Excel spreadsheet)
- **stream** (*bool, optional*) – Force PDF to be extracted using stream-mode extraction (if there are no ruling lines separating each cell, as in a PDF of an Excel spreadsheet)
- **password** (*str, optional*) – Password to decrypt document. Default: empty
- **silent** (*bool, optional*) – Suppress all stderr output.
- **columns** (*list, optional*) – X coordinates of column boundaries.

Example

```
[10.1, 20.2, 30.3]
```

- **format** (*str, optional*) – Format for output file or extracted object. ("CSV", "TSV", "JSON")
- **batch** (*str, optional*) – Convert all PDF files in the provided directory. This argument should be directory path.
- **options** (*str, optional*) – Raw option string for tabula-java.

Raises

- `FileNotFoundException` – If downloaded remote file doesn't exist.
- `ValueError` – If `output_format` is unknown format, or if downloaded remote file size is 0.
- `tabula.errors.JavaNotFoundError` – If java is not installed or found.
- `subprocess.CalledProcessError` – If tabula-java execution failed.

```
tabula.io.convert_into_by_batch(input_dir: str, output_format: str = 'csv', java_options: Optional[List[str]] = None, pages: Union[str, int, List[int], None] = None, guess: bool = True, area: Union[Iterable[float], Iterable[Iterable[float]], None] = None, relative_area: bool = False, lattice: bool = False, stream: bool = False, password: Optional[str] = None, silent: Optional[bool] = None, columns: Optional[List[float]] = None, relative_columns: bool = False, format: Optional[str] = None, output_path: Optional[str] = None, options: str = "") → None
```

Convert tables from PDFs in a directory.

Parameters

- **input_dir** (*str*) – Directory path.
- **output_format** (*str, optional*) – Output format of this function (csv, json or tsv)
- **java_options** (*list, optional*) – Set java options like `-Xmx256m`.
- **pages** (*str, int, list of int, optional*) – An optional values specifying pages to extract from. It allows `str`, `'int'`, `list of :int`. Default: `1`

Examples

```
'1-2,3', 'all', [1,2]
```

- **guess** (*bool, optional*) – Guess the portion of the page to analyze per page. Default `True` If you use “area” option, this option becomes `False`.

Note: As of tabula-java 1.0.3, guess option becomes independent from lattice and stream option, you can use guess and lattice/stream option at the same time.

- **area** (*list of float, list of list of float, optional*) – Portion of the page to analyze(`top, left, bottom, right`). Default is entire page.

Note: If you want to use multiple area options and extract in one table, it should be better to set `multiple_tables=False` for `read_pdf()`

Examples

```
[269.875,12.75,790.5,561], [[12.1,20.5,30.1,50.2], [1.0,3.2,10.5,40.2]]]
```

- **relative_area**(*bool, optional*) – If all area values are between 0-100 (inclusive) and preceded by '%', input will be taken as % of actual height or width of the page. Default False.
- **lattice**(*bool, optional*) – Force PDF to be extracted using lattice-mode extraction (if there are ruling lines separating each cell, as in a PDF of an Excel spreadsheet)
- **stream**(*bool, optional*) – Force PDF to be extracted using stream-mode extraction (if there are no ruling lines separating each cell, as in a PDF of an Excel spreadsheet)
- **password**(*str, optional*) – Password to decrypt document. Default: empty
- **silent**(*bool, optional*) – Suppress all stderr output.
- **columns**(*list, optional*) – X coordinates of column boundaries.

Example

```
[10.1, 20.2, 30.3]
```

- **relative_columns**(*bool, optional*) – If all values are between 0-100 (inclusive) and preceded by '%', input will be taken as % of actual width of the page. Default False.
- **format**(*str, optional*) – Format for output file or extracted object. ("CSV", "TSV", "JSON")
- **options**(*str, optional*) – Raw option string for tabula-java.

Returns Nothing. Outputs are saved into the same directory with *input_dir*

Raises

- `ValueError` – If *input_dir* doesn't exist.
- `tabula.errors.JavaNotFoundError` – If java is not installed or found.
- `subprocess.CalledProcessError` – If tabula-java execution failed.

```
tabula.io.read_pdf(input_path: Union[IO, str, os.PathLike], output_format: Optional[str] = None, encoding: str = 'utf-8', java_options: Optional[List[str]] = None, pandas_options: Optional[Dict[str, Any]] = None, multiple_tables: bool = True, user_agent: Optional[str] = None, use_raw_url: bool = False, pages: Union[str, int, List[int], None] = None, guess: bool = True, area: Union[Iterable[float], Iterable[Iterable[float]], None] = None, relative_area: bool = False, lattice: bool = False, stream: bool = False, password: Optional[str] = None, silent: Optional[bool] = None, columns: Optional[List[float]] = None, relative_columns: bool = False, format: Optional[str] = None, batch: Optional[str] = None, output_path: Optional[str] = None, options: str = '')) → Union[List[pandas.core.frame.DataFrame], Dict[str, Any]]
```

Read tables in PDF.

Parameters

- **input_path**(*str, path object or file-like object*) – File like object of target PDF file. It can be URL, which is downloaded by tabula-py automatically.
- **output_format**(*str, optional*) – Output format for returned object (dataframe or json) Giving this option enforces to ignore *multiple_tables* option.
- **encoding**(*str, optional*) – Encoding type for pandas. Default: utf-8
- **java_options**(*list, optional*) – Set java options.

Example

```
[ "-Xmx256m"]
```

- **pandas_options**(*dict, optional*) – Set pandas options.

Example

```
{'header': None}
```

Note: With *multiple_tables=True* (default), *pandas_options* is passed to *pandas.DataFrame*, otherwise it is passed to *pandas.read_csv*. Those two functions are different for accept options like *dtype*.

- **multiple_tables**(*bool*) – It enables to handle multiple tables within a page. Default: True

Note: If *multiple_tables* option is enabled, tabula-py uses not *pd.read_csv()*, but *pd.DataFrame()*. Make sure to pass appropriate *pandas_options*.

- **user_agent**(*str, optional*) – Set a custom user-agent when download a pdf from a url. Otherwise it uses the default *urllib.request* user-agent.
- **use_raw_url**(*bool*) – It enforces to use *input_path* string for url without quoting/dequoting. Default: False
- **pages**(*str, int, list of int, optional*) – An optional values specifying pages to extract from. It allows *str*, ‘int’, *list* of *int*. Default: 1

Examples

```
'1-2,3', 'all', [1,2]
```

- **guess**(*bool, optional*) – Guess the portion of the page to analyze per page. Default *True* If you use “area” option, this option becomes *False*.

Note: As of tabula-java 1.0.3, guess option becomes independent from lattice and stream option, you can use guess and lattice/stream option at the same time.

- **area** (*list of float, list of list of float, optional*) – Portion of the page to analyze(*top, left, bottom, right*). Default is entire page.

Note: If you want to use multiple area options and extract in one table, it should be better to set `multiple_tables=False` for `read_pdf()`

Examples

```
[269.875, 12.75, 790.5, 561], [[12.1, 20.5, 30.1, 50.2], [1.0, 3.2, 10.5, 40.2]]
```

- **relative_area** (*bool, optional*) – If all area values are between 0-100 (inclusive) and preceded by '%', input will be taken as % of actual height or width of the page. Default False.
- **lattice** (*bool, optional*) – Force PDF to be extracted using lattice-mode extraction (if there are ruling lines separating each cell, as in a PDF of an Excel spreadsheet)
- **stream** (*bool, optional*) – Force PDF to be extracted using stream-mode extraction (if there are no ruling lines separating each cell, as in a PDF of an Excel spreadsheet)
- **password** (*str, optional*) – Password to decrypt document. Default: empty
- **silent** (*bool, optional*) – Suppress all stderr output.
- **columns** (*list, optional*) – X coordinates of column boundaries.

Example

```
[10.1, 20.2, 30.3]
```

- **relative_columns** (*bool, optional*) – If all values are between 0-100 (inclusive) and preceded by '%', input will be taken as % of actual width of the page. Default False.
- **format** (*str, optional*) – Format for output file or extracted object. ("CSV", "TSV", "JSON")
- **batch** (*str, optional*) – Convert all PDF files in the provided directory. This argument should be directory path.
- **output_path** (*str, optional*) – Output file path. File format of it is depends on format. Same as --outfile option of tabula-java.
- **options** (*str, optional*) – Raw option string for tabula-java.

Returns list of DataFrames or dict.

Raises

- `FileNotFoundException` – If downloaded remote file doesn't exist.
- `ValueError` – If `output_format` is unknown format, or if downloaded remote file size is 0.
- `tabula.errors.CSVParseError` – If pandas CSV parsing failed.
- `tabula.errors.JavaNotFoundError` – If java is not installed or found.
- `subprocess.CalledProcessError` – If tabula-java execution failed.

Examples

Here is a simple example. Note that `read_pdf()` only extract page 1 by default.

Notes: As of tabula-py 2.0.0, `read_pdf()` sets `multiple_tables=True` by default. If you want to get consistent output with previous version, set `multiple_tables=False`.

```
>>> import tabula
>>> pdf_path = "https://github.com/chezou/tabula-py/raw/master/tests/resources/
   >>> data.pdf"
>>> tabula.read_pdf(pdf_path, stream=True)
[   Unnamed: 0  mpg  cyl  disp    hp  drat    wt  qsec    vs    am  gear
   carb
0      Mazda RX4  21.0     6  160.0  110  3.90  2.620  16.46    0     1     4
1      Mazda RX4 Wag  21.0     6  160.0  110  3.90  2.875  17.02    0     1     4
2      Datsun 710  22.8     4  108.0   93  3.85  2.320  18.61    1     1     4
3      Hornet 4 Drive  21.4     6  258.0  110  3.08  3.215  19.44    1     0     3
4      Hornet Sportabout  18.7     8  360.0  175  3.15  3.440  17.02    0     0     3
5      Valiant  18.1     6  225.0  105  2.76  3.460  20.22    1     0     3
6      Duster 360  14.3     8  360.0  245  3.21  3.570  15.84    0     0     3
7      Merc 240D  24.4     4  146.7   62  3.69  3.190  20.00    1     0     4
8      Merc 230  22.8     4  140.8   95  3.92  3.150  22.90    1     0     4
9      Merc 280  19.2     6  167.6  123  3.92  3.440  18.30    1     0     4
10     Merc 280C  17.8     6  167.6  123  3.92  3.440  18.90    1     0     4
11     Merc 450SE  16.4     8  275.8  180  3.07  4.070  17.40    0     0     3
12     Merc 450SL  17.3     8  275.8  180  3.07  3.730  17.60    0     0     3
13     Merc 450SLC  15.2     8  275.8  180  3.07  3.780  18.00    0     0     3
14     Cadillac Fleetwood  10.4     8  472.0  205  2.93  5.250  17.98    0     0     3
15     Lincoln Continental  10.4     8  460.0  215  3.00  5.424  17.82    0     0     3
16     Chrysler Imperial  14.7     8  440.0  230  3.23  5.345  17.42    0     0     3
17     Fiat 128  32.4     4   78.7    66  4.08  2.200  19.47    1     1     4
18     Honda Civic  30.4     4   75.7    52  4.93  1.615  18.52    1     1     4
19     Toyota Corolla  33.9     4   71.1    65  4.22  1.835  19.90    1     1     4
20     Toyota Corona  21.5     4  120.1    97  3.70  2.465  20.01    1     0     3
21     Dodge Challenger  15.5     8  318.0   150  2.76  3.520  16.87    0     0     3
22     AMC Javelin  15.2     8  304.0   150  3.15  3.435  17.30    0     0     3
   2
] (continues on next page)
```

(continued from previous page)

| | | | | | | | | | | | | | |
|----|---|------------------|------|---|-------|-----|------|-------|-------|---|---|---|---|
| 23 | | Camaro Z28 | 13.3 | 8 | 350.0 | 245 | 3.73 | 3.840 | 15.41 | 0 | 0 | 3 | ✉ |
| 24 | ↳ | Pontiac Firebird | 19.2 | 8 | 400.0 | 175 | 3.08 | 3.845 | 17.05 | 0 | 0 | 3 | ✉ |
| 25 | ↳ | Fiat X1-9 | 27.3 | 4 | 79.0 | 66 | 4.08 | 1.935 | 18.90 | 1 | 1 | 4 | ✉ |
| 26 | ↳ | Porsche 914-2 | 26.0 | 4 | 120.3 | 91 | 4.43 | 2.140 | 16.70 | 0 | 1 | 5 | ✉ |
| 27 | ↳ | Lotus Europa | 30.4 | 4 | 95.1 | 113 | 3.77 | 1.513 | 16.90 | 1 | 1 | 5 | ✉ |
| 28 | ↳ | Ford Pantera L | 15.8 | 8 | 351.0 | 264 | 4.22 | 3.170 | 14.50 | 0 | 1 | 5 | ✉ |
| 29 | ↳ | Ferrari Dino | 19.7 | 6 | 145.0 | 175 | 3.62 | 2.770 | 15.50 | 0 | 1 | 5 | ✉ |
| 30 | ↳ | Maserati Bora | 15.0 | 8 | 301.0 | 335 | 3.54 | 3.570 | 14.60 | 0 | 1 | 5 | ✉ |
| 31 | ↳ | Volvo 142E | 21.4 | 4 | 121.0 | 109 | 4.11 | 2.780 | 18.60 | 1 | 1 | 4 | ✉ |
| | ↳ | | 2] | | | | | | | | | | |

If you want to extract all pages, set pages="all".

```
>>> dfs = tabula.read_pdf(pdf_path, pages="all")
>>> len(dfs)
4
>>> dfs
[   0   1   2   3   4   5   6   7   8   9
0  mpg cyl disp hp drat   wt  qsec vs am gear
1 21.0   6 160.0 110 3.90 2.620 16.46 0  1    4
2 21.0   6 160.0 110 3.90 2.875 17.02 0  1    4
3 22.8   4 108.0  93 3.85 2.320 18.61 1  1    4
4 21.4   6 258.0 110 3.08 3.215 19.44 1  0    3
5 18.7   8 360.0 175 3.15 3.440 17.02 0  0    3
6 18.1   6 225.0 105 2.76 3.460 20.22 1  0    3
7 14.3   8 360.0 245 3.21 3.570 15.84 0  0    3
8 24.4   4 146.7  62 3.69 3.190 20.00 1  0    4
9 22.8   4 140.8  95 3.92 3.150 22.90 1  0    4
10 19.2   6 167.6 123 3.92 3.440 18.30 1  0    4
11 17.8   6 167.6 123 3.92 3.440 18.90 1  0    4
12 16.4   8 275.8 180 3.07 4.070 17.40 0  0    3
13 17.3   8 275.8 180 3.07 3.730 17.60 0  0    3
14 15.2   8 275.8 180 3.07 3.780 18.00 0  0    3
15 10.4   8 472.0 205 2.93 5.250 17.98 0  0    3
16 10.4   8 460.0 215 3.00 5.424 17.82 0  0    3
17 14.7   8 440.0 230 3.23 5.345 17.42 0  0    3
18 32.4   4  78.7  66 4.08 2.200 19.47 1  1    4
19 30.4   4  75.7  52 4.93 1.615 18.52 1  1    4
20 33.9   4  71.1  65 4.22 1.835 19.90 1  1    4
21 21.5   4 120.1  97 3.70 2.465 20.01 1  0    3
22 15.5   8 318.0 150 2.76 3.520 16.87 0  0    3
23 15.2   8 304.0 150 3.15 3.435 17.30 0  0    3
24 13.3   8 350.0 245 3.73 3.840 15.41 0  0    3
25 19.2   8 400.0 175 3.08 3.845 17.05 0  0    3
26 27.3   4  79.0  66 4.08 1.935 18.90 1  1    4
27 26.0   4 120.3  91 4.43 2.140 16.70 0  1    5
28 30.4   4  95.1 113 3.77 1.513 16.90 1  1    5
29 15.8   8 351.0 264 4.22 3.170 14.50 0  1    5
30 19.7   6 145.0 175 3.62 2.770 15.50 0  1    5
```

(continues on next page)

(continued from previous page)

| | | | | | | | | | | | | |
|----|--------------|--------------|--------------|--------------|-------------|------------|-------|---|---|----|---|---|
| 31 | 15.0 | 8 | 301.0 | 335 | 3.54 | 3.570 | 14.60 | 0 | 1 | 5, | 0 | ✉ |
| ↳ | 1 | | | 2 | | 3 | | 4 | | | | |
| 0 | Sepal.Length | Sepal.Width | Petal.Length | Petal.Width | Species | | | | | | | |
| 1 | 5.1 | 3.5 | 1.4 | 0.2 | setosa | | | | | | | |
| 2 | 4.9 | 3.0 | 1.4 | 0.2 | setosa | | | | | | | |
| 3 | 4.7 | 3.2 | 1.3 | 0.2 | setosa | | | | | | | |
| 4 | 4.6 | 3.1 | 1.5 | 0.2 | setosa | | | | | | | |
| 5 | 5.0 | 3.6 | 1.4 | 0.2 | setosa | | | | | | | |
| 6 | 5.4 | 3.9 | 1.7 | 0.4 | setosa, | 0 | | | | | | ✉ |
| ↳ | 1 | 2 | 3 | 4 | 5 | | | | | | | |
| 0 | NaN | Sepal.Length | Sepal.Width | Petal.Length | Petal.Width | Species | | | | | | |
| 1 | 145 | 6.7 | 3.3 | 5.7 | 2.5 | virginica | | | | | | |
| 2 | 146 | 6.7 | 3.0 | 5.2 | 2.3 | virginica | | | | | | |
| 3 | 147 | 6.3 | 2.5 | 5.0 | 1.9 | virginica | | | | | | |
| 4 | 148 | 6.5 | 3.0 | 5.2 | 2.0 | virginica | | | | | | |
| 5 | 149 | 6.2 | 3.4 | 5.4 | 2.3 | virginica | | | | | | |
| 6 | 150 | 5.9 | 3.0 | 5.1 | 1.8 | virginica, | 0 | | | | | |
| 0 | supp | | | | | | | | | | | |
| 1 | VC | | | | | | | | | | | |
| 2 | VC | | | | | | | | | | | |
| 3 | VC | | | | | | | | | | | |
| 4 | VC | | | | | | | | | | | |
| 5 | VC | | | | | | | | | | | |
| 6 | VC | | | | | | | | | | | |
| 7 | VC | | | | | | | | | | | |
| 8 | VC | | | | | | | | | | | |
| 9 | VC | | | | | | | | | | | |
| 10 | VC | | | | | | | | | | | |
| 11 | VC | | | | | | | | | | | |
| 12 | VC | | | | | | | | | | | |
| 13 | VC | | | | | | | | | | | |
| 14 | VC] | | | | | | | | | | | |

```
tabula.io.read_pdf_with_template(input_path: Union[IO, str, os.PathLike], template_path:
                                  Union[IO, str, os.PathLike], pandas_options: Optional[Dict[str, Any]] = None, encoding: str = 'utf-8',
                                  java_options: Optional[List[str]] = None, user_agent: Optional[str] = None, use_raw_url: bool = False, pages:
                                  Union[str, int, List[int], None] = None, guess: bool = False, area: Union[Iterable[float], Iterable[Iterable[float]],
                                  None] = None, relative_area: bool = False, lattice: bool = False, stream: bool = False, password: Optional[str]
                                  = None, silent: Optional[bool] = None, columns: Optional[List[float]] = None, relative_columns: bool = False,
                                  format: Optional[str] = None, batch: Optional[str] = None, output_path: Optional[str] = None, options: Optional[str] =
                                  None) → List[pandas.core.frame.DataFrame]
```

Read tables in PDF with a Tabula App template.

Parameters

- **input_path** (*str, path object or file-like object*) – File like object of target PDF file. It can be URL, which is downloaded by tabula-py automatically.
- **template_path** (*str, path object or file-like object*) – File like object for Tabula app template. It can be URL, which is downloaded by tabula-py automatically.

- **pandas_options** (*dict, optional*) – Set pandas options like { ‘header’: None}.
- **encoding** (*str, optional*) – Encoding type for pandas. Default is ‘utf-8’
- **java_options** (*list, optional*) – Set java options like [“-Xmx256m”].
- **user_agent** (*str, optional*) – Set a custom user-agent when download a pdf from a url. Otherwise it uses the default `urllib.request` user-agent.
- **use_raw_url** (*bool*) – It enforces to use *input_path* string for url without quoting/dequoting. Default: False
- **pages** (*str, int, list of int, optional*) – An optional values specifying pages to extract from. It allows *str*, ‘int’, *list of :int*. Default: 1

Examples

```
'1-2,3', 'all', [1,2]
```

- **guess** (*bool, optional*) – Guess the portion of the page to analyze per page. Default *True* If you use “area” option, this option becomes *False*.

Note: As of tabula-java 1.0.3, guess option becomes independent from lattice and stream option, you can use guess and lattice/stream option at the same time.

- **area** (*list of float, list of list of float, optional*) – Portion of the page to analyze(*top, left, bottom, right*). Default is entire page.

Note: If you want to use multiple area options and extract in one table, it should be better to set `multiple_tables=False` for `read_pdf()`

Examples

```
[269.875,12.75,790.5,561], [[12.1,20.5,30.1,50.2], [1.0,3.2,10.5,40.2]]
```

- **relative_area** (*bool, optional*) – If all area values are between 0-100 (inclusive) and preceded by ‘%’, input will be taken as % of actual height or width of the page. Default False.
- **lattice** (*bool, optional*) – Force PDF to be extracted using lattice-mode extraction (if there are ruling lines separating each cell, as in a PDF of an Excel spreadsheet)
- **stream** (*bool, optional*) – Force PDF to be extracted using stream-mode extraction (if there are no ruling lines separating each cell, as in a PDF of an Excel spreadsheet)
- **password** (*str, optional*) – Password to decrypt document. Default: empty
- **silent** (*bool, optional*) – Suppress all stderr output.
- **columns** (*list, optional*) – X coordinates of column boundaries.

Example

```
[10.1, 20.2, 30.3]
```

- **relative_columns** (bool, optional) – If all values are between 0-100 (inclusive) and preceded by '%', input will be taken as % of actual width of the page. Default False.
- **format** (str, optional) – Format for output file or extracted object. ("CSV", "TSV", "JSON")
- **batch** (str, optional) – Convert all PDF files in the provided directory. This argument should be directory path.
- **output_path** (str, optional) – Output file path. File format of it is depends on format. Same as --outfile option of tabula-java.
- **options** (str, optional) – Raw option string for tabula-java.

Returns list of DataFrame.

Raises

- FileNotFoundError – If downloaded remote file doesn't exist.
- ValueError – If output_format is unknown format, or if downloaded remote file size is 0.
- `tabula.errors.CSVParseError` – If pandas CSV parsing failed.
- `tabula.errors.JavaNotFoundError` – If java is not installed or found.
- subprocess.CalledProcessError – If tabula-java execution failed.

Examples

You can use template file extracted by tabula app.

```
>>> import tabula
>>> tabula.read_pdf_with_template(pdf_path, "/path/to/data.tabula-template.json")
[   Unnamed: 0  mpg  cyl  disp  hp  ...  qsec  vs  am  gear  carb
0      Mazda RX4  21.0    6  160.0  110  ...  16.46  0  1  4  4
1      Mazda RX4 Wag  21.0    6  160.0  110  ...  17.02  0  1  4  4
2      Datsun 710  22.8    4  108.0  93  ...  18.61  1  1  4  1
3      Hornet 4 Drive  21.4    6  258.0  110  ...  19.44  1  0  3  1
4      Hornet Sportabout  18.7    8  360.0  175  ...  17.02  0  0  3  2
5      Valiant  18.1    6  225.0  105  ...  20.22  1  0  3  1
6      Duster 360  14.3    8  360.0  245  ...  15.84  0  0  3  4
7      Merc 240D  24.4    4  146.7  62  ...  20.00  1  0  4  2
8      Merc 230  22.8    4  140.8  95  ...  22.90  1  0  4  2
9      Merc 280  19.2    6  167.6  123  ...  18.30  1  0  4  4
10     Merc 280C  17.8    6  167.6  123  ...  18.90  1  0  4  4
11     Merc 450SE  16.4    8  275.8  180  ...  17.40  0  0  3  3
12     Merc 450SL  17.3    8  275.8  180  ...  17.60  0  0  3  3
13     Merc 450SLC  15.2    8  275.8  180  ...  18.00  0  0  3  3
14     Cadillac Fleetwood  10.4    8  472.0  205  ...  17.98  0  0  3  4
15     Lincoln Continental  10.4    8  460.0  215  ...  17.82  0  0  3  4
16     Chrysler Imperial  14.7    8  440.0  230  ...  17.42  0  0  3  4
17      Fiat 128  32.4    4  78.7  66  ...  19.47  1  1  4  1
18      Honda Civic  30.4    4  75.7  52  ...  18.52  1  1  4  2
19      Toyota Corolla  33.9    4  71.1  65  ...  19.90  1  1  4  1
20      Toyota Corona  21.5    4  120.1  97  ...  20.01  1  0  3  1]
```

(continues on next page)

(continued from previous page)

| | | | | | | | | | | | |
|-------------------------|------------------|--------------|--------------|--------------|-------------|------------|-------|---|---|---|---|
| 21 | Dodge Challenger | 15.5 | 8 | 318.0 | 150 | ... | 16.87 | 0 | 0 | 3 | 2 |
| 22 | AMC Javelin | 15.2 | 8 | 304.0 | 150 | ... | 17.30 | 0 | 0 | 3 | 2 |
| 23 | Camaro Z28 | 13.3 | 8 | 350.0 | 245 | ... | 15.41 | 0 | 0 | 3 | 4 |
| 24 | Pontiac Firebird | 19.2 | 8 | 400.0 | 175 | ... | 17.05 | 0 | 0 | 3 | 2 |
| 25 | Fiat X1-9 | 27.3 | 4 | 79.0 | 66 | ... | 18.90 | 1 | 1 | 4 | 1 |
| 26 | Porsche 914-2 | 26.0 | 4 | 120.3 | 91 | ... | 16.70 | 0 | 1 | 5 | 2 |
| 27 | Lotus Europa | 30.4 | 4 | 95.1 | 113 | ... | 16.90 | 1 | 1 | 5 | 2 |
| 28 | Ford Pantera L | 15.8 | 8 | 351.0 | 264 | ... | 14.50 | 0 | 1 | 5 | 4 |
| 29 | Ferrari Dino | 19.7 | 6 | 145.0 | 175 | ... | 15.50 | 0 | 1 | 5 | 6 |
| 30 | Maserati Bora | 15.0 | 8 | 301.0 | 335 | ... | 14.60 | 0 | 1 | 5 | 8 |
| 31 | Volvo 142E | 21.4 | 4 | 121.0 | 109 | ... | 18.60 | 1 | 1 | 4 | 2 |
| [32 rows x 12 columns], | | | | | | | | | | | |
| 0 | | 0 | 1 | 2 | 3 | 4 | | | | | |
| 0 | NaN | Sepal.Width | Petal.Length | Petal.Width | Species | | | | | | |
| 1 | 5.1 | 3.5 | 1.4 | 0.2 | setosa | | | | | | |
| 2 | 4.9 | 3.0 | 1.4 | 0.2 | setosa | | | | | | |
| 3 | 4.7 | 3.2 | 1.3 | 0.2 | setosa | | | | | | |
| 4 | 4.6 | 3.1 | 1.5 | 0.2 | setosa | | | | | | |
| 5 | 5.0 | 3.6 | 1.4 | 0.2 | setosa, | | | | | | |
| 0 | | 0 | 1 | 2 | 3 | 4 | 5 | | | | |
| 0 | NaN | Sepal.Length | Sepal.Width | Petal.Length | Petal.Width | Species | | | | | |
| 1 | 145 | 6.7 | 3.3 | 5.7 | 2.5 | virginica | | | | | |
| 2 | 146 | 6.7 | 3.0 | 5.2 | 2.3 | virginica | | | | | |
| 3 | 147 | 6.3 | 2.5 | 5.0 | 1.9 | virginica | | | | | |
| 4 | 148 | 6.5 | 3.0 | 5.2 | 2.0 | virginica | | | | | |
| 5 | 149 | 6.2 | 3.4 | 5.4 | 2.3 | virginica, | | | | | |
| Unnamed: 0 supp dose | | | | | | | | | | | |
| 0 | | 4.2 | VC | 0.5 | | | | | | | |
| 1 | | 11.5 | VC | 0.5 | | | | | | | |
| 2 | | 7.3 | VC | 0.5 | | | | | | | |
| 3 | | 5.8 | VC | 0.5 | | | | | | | |
| 4 | | 6.4 | VC | 0.5 | | | | | | | |
| 5 | | 10.0 | VC | 0.5 | | | | | | | |
| 6 | | 11.2 | VC | 0.5 | | | | | | | |
| 7 | | 11.2 | VC | 0.5 | | | | | | | |
| 8 | | 5.2 | VC | 0.5 | | | | | | | |
| 9 | | 7.0 | VC | 0.5 | | | | | | | |
| 10 | | 16.5 | VC | 1.0 | | | | | | | |
| 11 | | 16.5 | VC | 1.0 | | | | | | | |
| 12 | | 15.2 | VC | 1.0 | | | | | | | |
| 13 | | 17.3 | VC | 1.0] | | | | | | | |

4.1.2 tabula.util

Utility module providing some convenient functions.

```
class tabula.util.TabulaOption(pages: Union[str, int, List[int], None] = None, guess: bool = True, area: Union[Iterable[float], Iterable[Iterable[float]], None] = None, relative_area: bool = False, lattice: bool = False, stream: bool = False, password: Optional[str] = None, silent: Optional[bool] = None, columns: Optional[List[float]] = None, relative_columns: bool = False, format: Optional[str] = None, batch: Optional[str] = None, output_path: Optional[str] = None, options: Optional[str] = "", multiple_tables: bool = True)
```

Bases: object

Build options for tabula-java

Parameters

- **pages** (str, int, list of int, optional) – An optional values specifying pages to extract from. It allows str, ‘int’, list of :int. Default: 1

Examples

```
'1-2,3', 'all', [1,2]
```

- **guess** (bool, optional) – Guess the portion of the page to analyze per page. Default True If you use “area” option, this option becomes False.

Note: As of tabula-java 1.0.3, guess option becomes independent from lattice and stream option, you can use guess and lattice/stream option at the same time.

- **area** (list of float, list of list of float, optional) – Portion of the page to analyze(top,left,bottom,right). Default is entire page.

Note: If you want to use multiple area options and extract in one table, it should be better to set `multiple_tables=False` for `read_pdf()`

Examples

```
[269.875,12.75,790.5,561], [[12.1,20.5,30.1,50.2], [1.0,3.2,10.5,40.2]]
```

- **relative_area** (bool, optional) – If all area values are between 0-100 (inclusive) and preceded by ‘%’, input will be taken as % of actual height or width of the page. Default False.
- **lattice** (bool, optional) – Force PDF to be extracted using lattice-mode extraction (if there are ruling lines separating each cell, as in a PDF of an Excel spreadsheet)
- **stream** (bool, optional) – Force PDF to be extracted using stream-mode extraction (if there are no ruling lines separating each cell, as in a PDF of an Excel spreadsheet)
- **password** (str, optional) – Password to decrypt document. Default: empty
- **silent** (bool, optional) – Suppress all stderr output.
- **columns** (list, optional) – X coordinates of column boundaries.

Example

```
[10.1, 20.2, 30.3]
```

- **relative_columns** (bool, optional) – If all values are between 0-100 (inclusive) and preceded by ‘%’, input will be taken as % of actual width of the page. Default False.
- **format** (str, optional) – Format for output file or extracted object. (“CSV”, “TSV”, “JSON”)

- **batch** (*str, optional*) – Convert all PDF files in the provided directory. This argument should be directory path.

- **output_path** (*str, optional*) – Output file path. File format of it is depends on format. Same as --outfile option of tabula-java.

- **options** (*str, optional*) – Raw option string for tabula-java.

- **multiple_tables** (*bool, optional*) – Extract multiple tables into a dataframe. Default: True

area = None

batch = None

build_option_list () → List[str]

Convert to tabula-java option list

columns = None

format = None

guess = True

lattice = False

merge (*other: tabula.util.TabulaOption*) → tabula.util.TabulaOption

Merge two TabulaOption. self will overwrite other fields' values.

multiple_tables = True

options = ''

output_path = None

pages = None

password = None

relative_area = False

relative_columns = False

silent = None

stream = False

tabula.util.environment_info () → None

Show environment information for reporting.

Returns Detailed information like Python version, Java version, or OS environment, etc.

Return type str

tabula.util.java_version () → str

Show Java version

Returns Result of java -version

Return type str

4.2 Internal interfaces

4.2.1 tabula.template

```
tabula.template.load_template(path_or_buffer: Union[IO, str, os.PathLike]) →  
List[tabula.util.TabulaOption]
```

Build tabula-py option from template file

Parameters `path_or_buffer` (`str, path object or file-like object`) – File like object of Tabula app template.

Returns tabula-py options

Return type dict

4.2.2 tabula.file_util

```
tabula.file_util.is_file_like(obj: Union[IO, str, os.PathLike]) → bool
```

Check file like object

Parameters `obj` – file like object.

Returns file like object or not

Return type bool

```
tabula.file_util.localize_file(path_or_buffer: Union[IO, str, os.PathLike], user_agent: Optional[str] = None, suffix: str = '.pdf', use_raw_url=False) →  
Tuple[str, bool]
```

Ensure localize target file.

If the target file is remote, this function fetches into local storage.

Parameters

- `path_or_buffer (str)` – File path or file like object or URL of target file.
- `user_agent (str, optional)` – Set a custom user-agent when download a pdf from a url. Otherwise it uses the default `urllib.request` user-agent.
- `suffix (str, optional)` – File extension to check.
- `use_raw_url (bool)` – Use `path_or_buffer` without quoting/dequoting.

Returns tuple of str and bool, which represents file name in local storage and temporary file flag.

Return type (str, bool)

CHAPTER 5

tabula.errors

```
exception tabula.errors.CSVParseError (message: Any, cause: Any)
```

Bases: pandas.errors.ParserError

Error represents CSV parse error, which mainly caused by pandas.

```
exception tabula.errors.JavaNotFoundError
```

Bases: Exception

Error represents Java doesn't exist.

CHAPTER 6

Indices and tables

- genindex
- modindex
- search

Python Module Index

t

tabula.errors, 29
tabula.file_util, 27
tabula.io, 13
tabula.template, 27
tabula.util, 24

Index

A

area (*tabula.util.TabulaOption attribute*), 26

B

batch (*tabula.util.TabulaOption attribute*), 26

build_option_list () (*tabula.util.TabulaOption method*), 26

C

columns (*tabula.util.TabulaOption attribute*), 26

convert_into () (*in module tabula.io*), 13

convert_into_by_batch () (*in module tabula.io*),
15

CSVParseError, 29

E

environment_info () (*in module tabula.util*), 26

F

format (*tabula.util.TabulaOption attribute*), 26

G

guess (*tabula.util.TabulaOption attribute*), 26

I

is_file_like () (*in module tabula.file_util*), 27

J

java_version () (*in module tabula.util*), 26

JavaNotFoundError, 29

L

lattice (*tabula.util.TabulaOption attribute*), 26

load_template () (*in module tabula.template*), 27

localize_file () (*in module tabula.file_util*), 27

M

merge () (*tabula.util.TabulaOption method*), 26

multiple_tables (*tabula.util.TabulaOption attribute*), 26

O

options (*tabula.util.TabulaOption attribute*), 26

output_path (*tabula.util.TabulaOption attribute*), 26

P

pages (*tabula.util.TabulaOption attribute*), 26

password (*tabula.util.TabulaOption attribute*), 26

R

read_pdf () (*in module tabula.io*), 16

read_pdf_with_template () (*in module tabula.io*), 21

relative_area (*tabula.util.TabulaOption attribute*),
26

relative_columns (*tabula.util.TabulaOption attribute*), 26

S

silent (*tabula.util.TabulaOption attribute*), 26

stream (*tabula.util.TabulaOption attribute*), 26

T

tabula.errors (*module*), 29

tabula.file_util (*module*), 27

tabula.io (*module*), 13

tabula.template (*module*), 27

tabula.util (*module*), 24

TabulaOption (*class in tabula.util*), 24